Nagios Log Server

Listening On Privileged Ports



Purpose

This document describes how to configure Nagios Log Server to listen on privileged ports (ports below 1024).

Target Audience

This document is intended for use by Nagios Log Server Administrators who would like configure Nagios Log Server to listen on ports below 1024 which are privileged in Linux. This can be useful if you have legacy devices that can only send on specific ports (e.g. syslog on port 514)

Background

Ports below 1024 are privileged on Linux and only allow the root user to listen on them. This document provides two solutions to this situation.

- 1. Run Logstash as root
- 2. Use setcap

Method 1: Run Logstash as root

This method configures logstash to run as the root user. Edit the file /etc/sysconfig/logstash by executing the following command:

vi /etc/sysconfig/logstash

When using the vi editor, to make changes press i on the keyboard first to enter insert mode. Press Esc to exit insert mode.

Find the line:

LS USER=nagios

1295 Bandana Blvd N, St. Paul, MN 55108 sales@nagios.com US: 1-888-624-4671 INTL: 1-651-204-9102

Nagios Log Server

Listening On Privileged Ports

Change the line to:

When you have finished, save the changes in vi by typing:

:wq

and press Enter.

Now proceed to the **Restart Logstash Service** section of this document.

Method 2: Use setcap

This option will preserve logstash running as the nagios user, however the following needs to be taken into consideration:

- This method may be less secure in some environments as it will allow any Java process to listen on privileged ports
- This option will work only on RHEL/CentOS 6.x. It will not work on RHEL/CentOS 7.x.

To use this method execute the following command:

```
echo -e "\nsetcap 'cap net bind service=+ep' \$(readlink -f \$(which java))" >> /etc/sysconfig/logstash
```

Now proceed to the Restart Logstash Service section of this document.

1295 Bandana Blvd N, St. Paul, MN 55108 sales@nagios.com US: 1-888-624-4671 INTL: 1-651-204-9102

Nagios Log Server

Listening On Privileged Ports

Restart Logstash Service

The logstash service needs to be restarted for these changes to apply:

RHEL / CentOS 6.x

service logstash restart

RHEL / CentOS 7.x

systemctl restart logstash.service

Please proceed to the Add Inputs section of this document.

Add Inputs

After implementing the chosen method you can add inputs to the configuration for ports below 1024. The following documentation explains how to create an input in Nagios Log Server:

Configuring Nagios Log Server Inputs

Note: Any ports lower than 1024 will not be listed in the "Logstash is currently collecting" banner on the Admin Overview page because the process listing the ports is not privileged and thus can not see any ports lower than 1024.

Finishing Up

This completes the documentation on how to configure Nagios Log Server to listen on privileged ports. If you have additional questions or other support related questions, please visit us at our Nagios Support Forums:

https://support.nagios.com/forum

The Nagios Support Knowledgebase is also a great support resource:

https://support.nagios.com/kb

1295 Bandana Blvd N, St. Paul, MN 55108 sales@nagios.com US: 1-888-624-4671 INTL: 1-651-204-9102