Purpose

This document describes how to passively monitor Windows hosts using NRDS_Win. NRDS_Win is a lightweight client which can process Nagios plugins and pass back check results. This passive agent sends results back to Nagios over port 80 (HTTP) or port 443 (HTTPS). This is advantageous for situations where Nagios can't reach the hosts you wish to monitor because of firewall rules, but the host is able to contact Nagios. Passive monitoring is very scalable since all check processing is done by the clients, sending back only results.

NRDS_Win also has the ability to automatically update its configuration and plugins. All configurations are centrally managed by the NRDS configuration manager making administration of large environments a snap. You can also use NRDS_Win as a NRDP sender if you're using Nagios Core and not utilizing the config administration capability.

If you are passive monitoring with NRDS in Nagios XI 2024, see Passive Monitoring with NRDS.

Configuring NRDP Inbound Transfers


Before you can receive passive check results from NRDS agents you need to configure NRDP Inbound Transfers. This can be done in Nagios XI by navigating to **Admin > Check Transfers > Inbound Transfers**.

Please refer to the following documentation for detailed steps on configuring NRDP:

Configuring Inbound Checks With XI

Using NRDS Config Manager

To use the NRDS Config Manager navigate to Admin > Monitoring Config > NRDS Config Manager:



www.nagios.com



Page 1 of 8

Adding Configuration

Click the **Create Config** button, select the desired **Operating System** (in this example we will be using Windows) and then click Next.

You will be presented with the **Edit NRDS Config** screen which will be prepopulated with some defaults.

Main Config

The **CONFIG_NAME** field is a name used to identify this config. Your remote clients will be requesting the config with this name, so once you deploy the clients you should not change the name of the config (otherwise you'll need to manually update the name of the configs on each client).

The **URL** field should be your NRDP server URL and this URL must be accessible from the client machines. It should be correctly populated by Nagios XI, however it can be changed if required.

The **TOKEN** drop down list will have a choice of valid tokens that have been set up in the NRDP server. You will have done this when you configured Inbound Transfers under **Admin > Check Transfers**.


Note: If you need to change your token on the NRDP server, it would be advised to add the new token to the NRDP server, then change it in the NRDS configs. Allow enough time for all your client machine to connect and download the new config before removing the old token from the NRDP server.

Commands

The commands are the checks you would like the client to run every time NRDS_Win is scheduled to run, the results will be returned to the Nagios server.

They are listed one per line in the following format:

command[SERVICE NAME]=\$PLUGIN_DIR\$\plugin_to_run ARGS





Create NRDS Config

Cancel

Windows (64-bit)

Operating System

Next >

One special **SERVICE NAME** is __HOST__ which is used to specify the HOST check, whereas all other checks will be identified by whatever is in place of **SERVICE NAME**.

Additional Settings

The settings here should only need to be changed for custom setups.

PLUGIN_DIR -The plugin location on the client machine. This location is substituted for \$PLUGIN_DIR\$ when the checks are run.

SEND_NRDP - Not used by NRDS_Win TMPDIR - Not used by NRDS_Win COMMAND_PREFIX - Not used by NRDS_Win

LOG_FILE - The location on the client machine where the log file will be stored.


IGNORE_SSL_CERTIFICATE_ERRORS - If you have enabled SSL on your Nagios XI server, you can submit checks back using SSL. If however you don't have a certificate authority defined for the client, you can choose to ignore certificate errors and check results will still be received

| Main Config | | 10 10-101 (K) 10 10 | |
|--|---|--|-----------------------------------|
| URL is the NRDP U | RL on this server. The U | RL must be reachable by the client. | |
| VERSION: | 0 | | |
| CONFIG_NAME | NRDS_Windows_64 | | |
| URL | http://10.25.5.23/nrdg | / | |
| TOKEN | IHnHUbsp7daj 🔻 | | |
| Commands | | | |
| (One per line) forr command[SERVIC | nat: :E_NAME]=/path/to/chec | k_plugin ARGS | |
| command[Disk 5 command[Event command[Memory command[Physic | <pre>pace] = \$PLUGIN_DIR Log] = \$PLUGIN_DIR\$ v Usage] = \$PLUGIN_D al Memory Usage] = 1</pre> | <pre>:heck_cpu.ps1 -w 70 -c 90 ;\check_pdm.exediskdrive C ,eventlog_nrpe_nt.exe -m 7200 .R\$\\check_pdm.exememory -w 90 SPLUGIN_DIR\$\check_pdm.exememory -w 90</pre> | -c 99 |
| command[Disk 9 command[Event command[Memory] command[Physic command[Servic | <pre>space] = \$PLUGIN_DIR: Log] = \$PLUGIN_DIR\$ / Usage] = \$PLUGIN_D. al Memory Usage] =: es] = \$PLUGIN_DIR\$\; tings</pre> | <pre>i\check_pdm.exediskdrive C ,eventlog_nrpe_nt.exe -m 7200 R\$\check_pdm.exememory -w 90</pre> | -c 99 |
| command[Disk 5 command[Event command[Memory command[Physic command[Servio Additional Sett | <pre>space] = \$PLUGIN_DIR: Log] = \$PLUGIN_DIR\$ / Usage] = \$PLUGIN_D. al Memory Usage] =: es] = \$PLUGIN_DIR\$\; tings</pre> | <pre>\\check_pdm.exediskdrive C .eventlog_nrpe_nt.exe -m 7200 R\$\check_pdm.exememory -w 90 PPLUGIN_DIR\$\check_pdm.exemem ervice_nrpe_nt.exe "DNS Client"</pre> | -c 99 ry pagefile -w 80 -c 95 |
| command[Disk S command[Pevent command[Pevent command[Physic command[Servic | <pre>space] = \$PLUGIN_DIR: Log] = \$PLUGIN_DIR\$ / Usage] = \$PLUGIN_D. al Memory Usage] =: es] = \$PLUGIN_DIR\$\; tings</pre> | <pre>i\check_pdm.exediskdrive C eventlog_nrpe_nt.exe -m 7200 PUUGIN_DIRS\check_pdm.exememory -w 0 PUUGIN_DIRS\check_pdm.exemem evervice_nrpe_nt.exe "DNS Client" ns and aren't normally changed.</pre> | -c 99 ry pagefile -w 80 -c 95 |
| command[Disk 5 command[Event command[Physic command[Physic command[Servic Additional Sett These items are for PLUGIN_DIR SEND_NRDP | <pre>space] = \$PLUGIN_DIR: Log] = \$PLUGIN_DIR\$ / Usage] = \$PLUGIN_D. al Memory Usage] =: es] = \$PLUGIN_DIR\$\; tings</pre> | <pre>i\check_pdm.exediskdrive C eventlog_nrpe_nt.exe -m 7200 PUUGIN_DIRS\check_pdm.exememory -w 0 PUUGIN_DIRS\check_pdm.exemem evervice_nrpe_nt.exe "DNS Client" ns and aren't normally changed.</pre> | -c 99 ry pagefile -w 80 -c 95 |
| command[Disk S command[Wemory command[Physic command[Physic command[Physic command[Servic Additional Sett These items are for PLUGIN_DIR SEND_NRDP TMPDIR | <pre>space] = \$PLUGIN_DIR; Log] = \$PLUGIN_DIR\$ / Usage] = \$PLUGIN_DIR\$.al Memory Usage] = : :es] = \$PLUGIN_DIR\$ tings or advanced configuratio</pre> | <pre>i\check_pdm.exediskdrive C eventlog_nrpe_nt.exe -m 7200 PUUGIN_DIRS\check_pdm.exememory -w 0 PUUGIN_DIRS\check_pdm.exemem evervice_nrpe_nt.exe "DNS Client" ns and aren't normally changed.</pre> | -c 99 ry pagefile -w 80 -c 95 |
| command[Disk 3 command[Kemory command[Physic command[Physic command[Servic Additional Sett These items are for PLUGIN_DIR SEND_NRDP TMPDIR COMMAND_PREI | <pre>space] = \$PLUGIN_DIR; Log] = \$PLUGIN_DIR\$ / Usage] = \$PLUGIN_DIR\$.al Memory Usage] = : :es] = \$PLUGIN_DIR\$ tings or advanced configuratio</pre> | <pre>i\check_pdm.exediskdrive C eventlog_nrpe_nt.exe -m 7200 PUUGIN_DIRS\check_pdm.exememory -w 0 PUUGIN_DIRS\check_pdm.exemem evervice_nrpe_nt.exe "DNS Client" ns and aren't normally changed.</pre> | -c 99 pry pagefile -w 80 -c 95 |
| command[Disk] command[Event command[Physic command[Physic command[Physic command[Service Additional Sett These items are for PLUGIN_DIR SEND_NRDP TMPDIR COMMAND_PREID LOG_FILE | <pre>space] = \$PLUGIN_DIR; Log] = \$PLUGIN_DIR\$ / Usage] = \$PLUGIN_DIR\$.al Memory Usage] = : :es] = \$PLUGIN_DIR\$ tings or advanced configuratio</pre> | <pre>\\check_pdm.exediskdrive C .eventlog_nrpe_nt.exe -m 7200 RS\check_pdm.exememory -w 90 PPLUGIN_DIRS\check_pdm.exemem .ervice_nrpe_nt.exe "DNS Client" ns and aren't normally changed. C:\Program Files\Nagios\NRDS_Win\</pre> | -c 99 pry pagefile -w 80 -c 95 |
| command[Disks' command[Event command[Physic command[Physic command[Physic command[Service Additional Sett These items are for PLUGIN_DIR SEND_NRDP TMPDIR COMMAND_PREID LOG_FILE | <pre>space] = \$PLUGIN_DIR: Log] = SPLUGIN_DIRS / Usage] = SPLUGIN_DIRS / usage] = SPLUGIN_DIRS / tings r advanced configuratio FIX ERTIFICATE_ERRORS</pre> | <pre>i\check_pdm.exediskdrive C eventlog_nrpe_nt.exe -m 7200 RS\check_pdm.exememory -w 90 PUUGIN_DIRS\check_pdm.exemem ervice_nrpe_nt.exe "DNS Client" ns and aren't normally changed. C:\Program Files\Nagios\NRDS_Win\ C:\Program Files\Nagios\NRDS_Win\</pre> | -c 99 pry pagefile -w 80 -c 95 |

UPDATE_CONFIG - If set to yes, the clients will all update their config files when changes are made.

UPDATE_PLUGINS - If set to yes, the clients will download new plugins if defined in the config file and they don't currently have them downloaded.

Once you've completed making all the changes, click the **Save** button. After the configuration is created it will appear in the list:



www.nagios.com



Actions

In the list of configs there are four icons in the actions column which are explained as follows:

🧔 Edit

Edit the existing config

Client Install Instructions

Please refer to the following section which explains this

Download Client

You can download a .exe file of the client with the configs

🗎 Delete

This will remove the config, once deleted the clients will not longer be able to receive any updates

Client Installation Instructions

By clicking on the Client Install Instructions you will be presented with the download file of the client that needs to be installed on every machine that will be using this configuration (as an administrator).

When you run the NRDS_Win.exe installer you'll notice it includes your NRDP URL, Token and

Configuration Name already populated. If they are not, you will need to provide them yourself.

You'll also need to provide:

HOSTNAME - The name the client will send to the Nagios server as the host.

INTERVAL - The frequency in minutes that you want the checks to be run. (1-59)

The install process will perform the following operations:

- Install NRDS client
- Create scheduled task
- Download plugins from NRDP server
- Send initial check results to Nagios

| igios Enterprises LLC | | (News) |
|--------------------------|-------------------------|--------|
| NRDS for Windows R4 | | U |
| -NRDS Configuration | | |
| NRDP URL | http://10.25.5.23/nrdp/ | |
| Token | IHnHUbsp7daj | |
| Configuration Name | NRDS_Windows_64 | |
| Host Name | 10.25.14.5 | |
| Time Interval | 5 Minute(s) | |
| | | |
| | | |
| oft Install System v2.46 | | |

www.nagios.com



Page 4 of 8

Once the client starts sending results, if the host/service has not been configured yet it will be found under **Admin > Monitoring Config > Unconfigured Objects**. From here the received check results can be used to create the required services using the Unconfigured Object wizard. More information on the Unconfigured Objects and passive services can be found in the following documentation:

Monitoring Unconfigured Objects With Nagios XI

Configuring Passive Services With Nagios XI

Client Installation Alternatives

Below are two alternative methods for installing the NRDS_Win, however they are not covered in this document.

You can download the latest NRDS_Win from exchange.nagios.org:

If you're using an automated deployment tool, you can install using the silent install line:

NRDS_WinR3-64.exe /S /NRDP="http://2.3.5.7/nrdp" /TOKEN=token /CONFIG=Windows64 /HOST=Callisto /INTERVAL=5

Plugins

Any plugins you want to run on the client machines should be loaded into the appropriate plugin subdirectory on the Nagios XI server. The base location is:

/usr/local/nrdp/plugins

Plugins should be placed in the folder that best matches their OS, then architecture of the machine. NRDS will search for the best available plugin by searching in the following order:

/usr/local/nrdp/plugins/\$0S\$/\$ARCH\$/\$0S_VER\$
/usr/local/nrdp/plugins/\$0S\$/\$ARCH\$
/usr/local/nrdp/plugins/\$0S\$
/usr/local/nrdp/plugins/Generic/\$ARCH\$
/usr/local/nrdp/plugins/Generic
/usr/local/nagios/libexec

This allows the same config to deliver plugins specific to different OS/architecture.

The <u>Nagios Exchange</u> includes a listing of thousands of useful plugins which can be integrated with Nagios XI. Here is an example of downloading the following two plugins as an example.

- Powershell plugin for checking for installed applications
- vbscript plugin for returning information about what configuration the client is running

www.nagios.com



Page 5 of 8

Open a terminal session to your Nagios XI server as the root user.

Change directories to where your plugins are stored by executing the following command:

cd /usr/local/nrdp/plugins/Windows/

Download the plugins from exchange executing the two commands:

```
wget https://exchange.nagios.org/directory/Plugins/Software/check_NRDS_config/details
waet\
https://exchange.nagios.org/directory/Plugins/Operating\Systems/Windows/check_windows_app_installs/details
```

Change the permissions and owner of the downloaded files:

chmod +x check_NRDS_config.vbs chmod +x check_windows_app_installs.ps1 chown nagios:nagios check_NRDS_config.vbs chown nagios:nagios check_windows_app_installs.ps1

```
[root@xi-r5x-x86 ~]# cd /usr/local/nrdp/plugins/Windows/
[root@xi-r5x-x86 Windows]# wget https://exchange.nagios.org/directory/Plugins/Software/check NRDS config/visit -0 che
ck NRDS config.vbs
2016-12-14 11:55:08 (1.64 MB/s) - `check NRDS config.vbs' saved [2597/2597]
[root@xi-r5x-x86 Windows]# wget https://exchange.nagios.org/directory/Plugins/Operating-Systems/Windows/check windows
_app_installs/visit -O check_windows_app_installs.ps1
2016-12-14 11:55:21 (2.00 MB/s) - `check_windows_app_installs.ps1' saved [2699/2699]
[root@xi-r5x-x86 Windows]# chmod +x check NRDS config.vbs
[root@xi-r5x-x86 Windows]# chmod +x check windows app installs.ps1
[root@xi-r5x-x86 Windows]# chown nagios:nagios check_NRDS_config.vbs
[root@xi-r5x-x86 Windows]# chown nagios:nagios check_windows_app_installs.ps1
```

Navigate to Admin > Monitoring Config > NRDS Config Manager.

Click the edit icon under Actions for the config that you want to add the plugins to.

Add the following check commands to your config via the **Command** text box:

command[NRDS_config_ver] =

"CONFIG VERSION"



command[delta_install] = \$PLUGIN_DIR\$\check_windows_app_installs.ps1

www.nagios.com



Page 6 of 8

Here is the updated configuration which will be downloaded and run by all clients:


```
command[_HOST__] = $PLUGIN_DIR$\check_winping.exe -H 127.0.0.1 --warning 200,40% --critical 400,80%
command[Processes] = $PLUGIN_DIR$\check_winprocess.exe --warning 40 --critical 50
command[CPU Load] = $PLUGIN_DIR$\check_cpu.ps1 -w 70 -c 90
command[Disk Space] = $PLUGIN_DIR$\check_cpu.exe --disk --drive C: -w 97.5 -c 99.5
command[Event Log] = $PLUGIN_DIR$\check_pdm.exe -memory -w 90 -c 99
command[Memory Usage] = $PLUGIN_DIR$\check_pdm.exe --memory pagefile -w 80 -c 95
command[Services] = $PLUGIN_DIR$\check_NRDS_config.ybs "..\config.ini" "settings" "CONFIG_VERSION"
command[NRDS_config_ver] = $PLUGIN_DIR$\check_windows_app_installs.ps1
```

Once the client downloads the plugins and starts sending back check results you'll need to create the required services using the Unconfigured Object wizard (**Admin > Monitoring Config > Unconfigured Objects**).

Troubleshooting With NRDS_Debug.log

To verify that NRDS_Win has successfully sent the service check data to Nagios XI, you can check the NRDS_Debug.log file. The default location is C:\Program Files\Nagios\NRDS_Win\logs but you can change the log directory and file name by editing the LOG_FILE setting specified in the NRDS config.

The screen below shows that Nagios has responded saying that all 7 included checks have completed.



If NRDS_Debug.log doesn't exist, verify the windows scheduled was created successfully and is running.

www.nagios.com



Finishing Up

This completes the documentation on passively monitoring with NRDP. If you have additional questions or other support-related questions, please visit us at our Nagios Support Forum, Nagios Knowledge Base, or Nagios Library:

Visit Nagios Support Forum

<u>Visit Nagios Knowledge Base</u>

Visit Nagios Library

www.nagios.com



Page 8 of 8