


Understanding Email Sending In Nagios Fusion 2026R2

Purpose

This document describes how to configure email sending in Nagios Fusion 2026R2.


Navigation

To access your email settings, navigate to **Administration > Settings > Notifications**:



Activating Email Notifications


To enable email notifications, switch on the **Enable Mail Notifications** toggle in the top **Notification Settings** section:



Understanding Email Sending In Nagios Fusion 2026R2


Mail Settings

In the **Mail Settings** section, define the **From** address for mail sent from Fusion, and check the SMTP checkbox:



The Mail Settings form is a light gray rounded rectangle. It has a title bar with an envelope icon and the text 'Mail Settings'. Below the title bar, there are two main sections. The first section is labeled 'From' and contains a text input field with the value 'address@awesomecompany.tld'. Below the input field is a small gray text label 'Send mail from this email.'. The second section is labeled 'Mailer' and contains a text label 'Choose how email notifications are sent.' followed by a radio button and the text 'SMTP'. At the bottom right of the form is a blue button with the text 'Save'.

In the **SMTP Settings** section add the SMTP settings for the account you'd like to use to send notifications:



The SMTP Settings form is a light gray rounded rectangle. It has a title bar with an envelope icon and the text 'SMTP Settings'. Below the title bar, there are four main sections. The first section is labeled 'Host' and contains a text input field with the value 'smtp.awesomecompany.tld'. Below the input field is a small gray text label 'Your SMTP server host.'. The second section is labeled 'Port' and contains a text input field with the value '587'. Below the input field is a small gray text label 'Your SMTP server port.'. The third section is labeled 'User' and contains a text input field with the value 'nagiosalerts@awesomecompany.tld'. Below the input field is a small gray text label 'Your SMTP server user / username.'. The fourth section is labeled 'Password' and contains a password input field with 12 dots and an eye icon. Below the input field is a small gray text label 'Your SMTP server password.'. At the bottom left of the form is a section labeled 'Encryption' with the text 'Choose how email notifications are sent.' and three radio buttons: 'None', 'STARTTLS' (which is selected), and 'SSL/TLS'. At the bottom right of the form is a blue button with the text 'Save'.

Understanding Email Sending In Nagios Fusion 2026R2

Sending a Test Email

To test your mail settings, click the **Send Test Notification** button on the upper right of the Notifications menu.



Finishing Up

This completes the documentation on Understanding Email Sending in Fusion 2026R2. If you have additional questions or other support-related questions, please visit the Nagios Support Forum, Nagios Documentation Hub, or Nagios Library:

[Visit Nagios Support Forum](#)

[Visit Documentation Hub](#)

[Visit Nagios Library](#)