

How To Use Views In Nagios Fusion 2026R2

Purpose

This document describes how to use Views in Nagios Fusion 2026R2.

Views Overview

Views provide a rotating display of custom Dashboards, so are a great option for providing a stream of visualizations to a NOC screen display.


Before configuring Views, you'll want to first create Dashboards.

This document provides details on creating and managing Dashboards:

[Using Dashboards in Nagios Fusion](#)

Accessing and Creating Views

To access Views and create a new one, navigate to the **Views** menu, then click **+ Add View**.



How To Use Views In Nagios Fusion 2026R2

Next, give the view a **Title**, select the **Dashboards** to make a part of it, then click **Submit**.

Add View

Create a new view here. Click submit when you are done.

Title

Great View

Dashboards

St. Paul DCPhoenix DCMain HUD

☒ (Select All)

☒ St. Paul DC

☒ Phoenix DC

☒ Main HUD

CancelSubmit

Clear

Close

The new view will now appear in the list:

Nagios Fusion

Search Fusion

Home

Fused Servers

Dashboards

Views

Help

Administration

Views

Views

View and manage all views

Search...

Search

10

1 of 1

Title	User	Dashboards
Great View	nagiosadmin	St. Paul DCPhoenix DCMain HUD

10

1 of 1

How To Use Views In Nagios Fusion 2026R2

View Options

Above a View, you will find a bar of options.

Fullscreen View

To fullscreen a View, click the square icon.



Start/Stop Views

To start or stop View rotation, click the play/stop button.



Move to Previous/Next Dashboard

To move to the previous or next Dashboard, click the left/right arrows.



Adjust View Rotation Speed

To adjust the speed of the View rotation between Dashboards, click the clock icon and use the slider increase or decrease.



Managing Views

Editing a View


To edit a View title or the dashboards that make it up from within a view, click **Edit View**.



How To Use Views In Nagios Fusion 2026R2


Editing and Deleting a View

If you haven't yet chosen a default view (see following section), you can use the **Actions** dropdown in the top-level Views menu to Edit, Delete, and Set default:



Making a View Your Default

You can click the star icon to make a view your default. Note that once you do so, the original top-level Views menu will be replaced by the default view when you access Views, and view management will be carried out with the in-view management dropdown, where you can search for, load, create, and delete views:



How To Use Views In Nagios Fusion 2026R2


Views Permissions

Views permissions are determined by Roles. You can learn more about managing Roles here:

[Managing Users and Roles in Nagios Fusion](#)

Note that if a checkbox in the Views settings is left unchecked, users with the Role will only have access to the ability on their own Views.

The one exception is the **Create** checkbox, which determines whether the user can create Views at all. In this example, users with this Role would be able to create, view, update, and delete only their own Views.



System Permissions	All	Create	View	Update	Delete
Dashboards If empty users only have access to their own.	☐	☒	☐	☐	☐
Views If empty users only have access to their own.	☐	☒	☐	☐	☐
Servers Control access to all fused servers.	☐	☐	☒	☐	☐

Finishing Up

This completes the documentation on Using Views in Nagios Fusion 2026R2. If you have additional questions or other support-related questions, please visit the Nagios Support Forum, Nagios Documentation Hub, or Nagios Library:

[Visit Nagios Support Forum](#)

[Visit Documentation Hub](#)

[Visit Nagios Library](#)