

# How To Use Automatic Login in Nagios XI 2026


## Purpose

This document describes how to use the Automatic Login feature in Nagios XI 2026. This enables you to configure Nagios XI to automatically log visitors in as a specific user when your Nagios XI interface URL is visited, or to add an Automatic Login button to the Login page which can be clicked to log in as a specific user without the need to authenticate.

This can be useful in scenarios where you'd like to share things like [status overviews](#), custom [Dashboards](#), and [Reports](#) with a wider audience without needing to share any login credentials, or for users to retain them. For example, the Auto-Login button could be linked to a read-only user, and used by managers and less technical staff to see how your infrastructure is performing.

## Finding Automatic Login

To begin, navigate to **Admin > System Config > Automatic Login**. Here you will find all of the settings for this feature:




# How To Use Automatic Login in Nagios XI 2026

## Configuring Automatic Login

Here you will see various settings:

- **Enable Automatic Login:** checking this box will enable Automatic Login.
- **Bypass Login Page:** checking this box will automatically log visitors to your Nagios XI URL into the user interface as the selected user without the opportunity to log in as a different user. In order to log in as a different user, visitors will need to log out to get to the Login page, then enter their credentials. Use this option with caution, it is the least secure approach.
- **Account:** this is the account which visitors will be logged into automatically, either immediately upon visiting the Nagios XI URL if **Bypass Login Page** is selected, or by clicking the Auto-Login button on the Login page. In most cases, a read-only user is chosen to protect the system, but any account can be used.

Once enabled, the login page will include the **Auto-Login** button:



The screenshot shows the Nagios XI login page with a dark blue background. At the top, it says "Welcome" and "Sign in to Nagios XI". Below this are two input fields: "Username" and "Password". The "Password" field is masked with dots. To the right of the "Password" field is a link that says "Forgot Password?". Below the input fields are two blue buttons: "Login" and "Auto-Login". The "Auto-Login" button is highlighted with a yellow border. At the bottom of the page, there are three icons with labels: "Phone", "Sales", and "Forum".

# How To Use Automatic Login in Nagios XI 2026

## Finishing Up

This completes the documentation on Using Automatic Login in Nagios XI 2026. If you have additional questions or other support-related questions, please visit us at our Nagios Support Forum, Nagios Documentation Hub, or Nagios Library:

[Visit Nagios Support Forum](#)

[Visit Documentation Hub](#)

[Visit Nagios Library](#)