



Purpose

This document describes how to manually install Nagios Log Server v2 (**Legacy**) from source on a clean Linux system.

Target Audience

This document is written for administrators who are looking to perform a new installation of Nagios Log Server on a Linux machine, rather than using a pre-configured virtual machine image.

Platform Support

See [Nagios Software / Operating System \(OS\) Supported Versions](#)

Installation Prerequisites

Important: Nagios Enterprises highly recommends and will only support installing Nagios Log Server on a newly installed, "clean" system (a bare minimal install with nothing else installed or configured).

Attempting to install Nagios Log Server on a pre-existing system with other applications already installed can cause the Nagios Log Server installation process to fail, critical system components and settings (e.g. database servers) to be modified in a way that negatively affects other applications, and previously installed applications to be automatically upgraded or removed. While installing Log Server on a system with other applications is possible, it is not recommended due to the possible interactions and complexity of multiple components that are required for Nagios Log Server to function. If you choose to ignore these warnings, you do so at your own risk.

Other Nagios products (XI, Network Analyzer and Fusion) should not co-exist on the same server.

Internet access is required for installation and upgrades!

Terminal Access

These instructions require you to establish a terminal session to the server you plan to install Nagios Log Server on. You will need to login to your server as the root user to perform the installation.

Install Nagios Log Server

Issue the following commands in your terminal session:

```
cd /tmp
wget https://assets.nagios.com/downloads/nagios-log-server/2/nagioslogserver-2.1.15.tar.gz
tar xzf nagioslogserver-2.1.15.tar.gz
cd nagioslogserver
./fullinstall
```

Note: If you need to install a specific version of Nagios Log Server, please visit the following page of Nagios Log Server versions to obtain the URL, use that in the `wget` command above, and the name of the specific file downloaded in the `tar` command:

<https://assets.nagios.com/downloads/nagios-log-server/versions.php>

Please proceed to the [Finalize Installation](#) section.

Finalize Installation

Once the installation has completed you should see a message like the following:

```
Nagios Log Server Installation Success!
```

You can finish the final setup steps for Nagios Log Server by visiting:


```
http://<server_ip_address>/nagioslogserver
```

Navigate to the user interface by using the URL provided in your terminal session.

You will be presented with the **Final Installation Steps** screen just like this:

Select **Install** if this is the first server in your Nagios Log Server cluster.

Select **Connect** if you want to add this server top an existing Nagios Log Server cluster. Please refer to the following Nagios Log Server documentation [Adding Additional Instances to Cluster](#) for detailed instructions.



Nagios Log Server Manual Installation Instructions

You will be presented with a page of fields that need to be populated before proceeding.

If you have already purchased Nagios Log Server you can add your license key here.

Nagios[®] LS Install

Final Installation Steps

You're almost done. Setup your instance or connect to existing cluster.

License Setup
Choose a trial license, enter your key, or [get a license now](#).

Free 60 day trial I already have a key

License Key

Admin Account Setup
Enter the admin account settings. The default username is nagiosadmin.

Username

Password

Confirm Password

Email

Language

Timezone

[Back](#) [Finish Installation](#)


Nagios Log Server [About](#) | [Legal](#) | Copyright © 2014-2017 Nagios Enterprises, LLC

Under **Admin Account Setup** please populate the fields as they are all required to continue.

Once you are ready click **Finish Installation** to save these settings.

Nagios Log Server Manual Installation Instructions

Please wait while the settings are applied to the server, once complete you will be presented with the Login screen with the status of **Installation Complete**.



Nagios LS Navigation

Login

Installation Complete!

Username

Password

Keep me logged in

[Log In](#) [Forgot your password?](#)

About Nagios Log Server

Nagios Log Server is an enterprise-class log analysis solution that provides organizations with insight into logged errors before problems affect critical business processes. For more information on Nagios Log Server, visit the [Nagios Log Server product page](#).

Nagios Learning Opportunities

Learn about Nagios [training](#) and [certification](#) programs.

Want to learn about how other experts are utilizing Nagios? Do not miss your chance to attend the next [Nagios World Conference](#).

Contact Us

Have a question or technical problem? Contact us today:

Support: [Online Support Forum](#)
 Phone: (651) 204-9102


Sales: Fax: (651) 204-9103
 Email: sales@nagios.com

Web: www.nagios.com

Nagios Log Server [About](#) | [Legal](#) | Copyright © 2014-2017 Nagios Enterprises, LLC

Type the username and password required to login to Nagios Log Server and then click the **Log In** button to begin.

You will be logged into Nagios Log Server and be placed at the home screen.



Finishing Up

Nagios Log Server will now be installed on your system, ready to start collecting logs.

If you have never used Nagios Log Server before then the following documentation is a great starting point to familiarize yourself with the [Technical Overview and Terminology Definitions](#).

Please refer to the [Nagios Log Server Administrator Guide](#) which will help get you started using Nagios Log Server.

Schedule a Quickstart: <https://www.nagios.com/services/quickstart/nagios-log-server/>

Contact Sales: sales@nagios.com

Nagios Support Forums: <https://support.nagios.com/forum>

The Nagios Support Knowledgebase: <https://support.nagios.com/kb>

1295 Bandana Blvd N, St. Paul, MN 55108 sales@nagios.com US: 1-888-624-4671 INTL: 1-651-204-9102