

Using The Core Config Manager For Host Management In Nagios XI 2024 And 2026

Purpose

This document describes how to manage hosts, host groups and host templates using the Nagios XI Core Config Manager (CCM). While monitoring wizards make it easy to set up new hosts in Nagios XI, the CCM allows for more precise control over host monitoring, notifications, and configurations.

Core Config Manager Overview

Hosts can most easily be set up using the Monitoring Wizard under the main Configure page. Some administrators may need more customized options, or a greater degree of control over their monitoring setup. The Nagios XI CCM allows for precise control over host monitoring, notifications, and configurations.

You can access the CCM from the Configure option on the top menu, and then select the Core Config Manager option under the Advanced Configuration option, or when you hover your mouse on the Configure option on the top menu it will appear as an option.

This document will discuss how to do the following items:


- [Adding hosts](#)
- [Modifying hosts](#)
- [Deleting hosts](#)
- [Copying hosts](#)
- [Managing host groups](#)
- [Using host templates](#)

Adding Hosts

1. To manually add a new host, select the **Hosts link** located under **Monitoring** on the left menu of CCM.

Using The Core Config Manager For Host Management In Nagios XI 2024 And 2026

- This will bring up the **Host Management** page, which displays a list of the current hosts being monitored by Nagios XI.



- Click the **Add New** button to manually add a host.

Using The Core Config Manager For Host Management In Nagios XI 2024 And 2026

4. The **Host Management** page will open on the **Common Settings** tab. This tab allows you to define the primary host parameters such as **Host Name**, **Description**, **Address**, and **Display name**.

The screenshot shows the 'Host Management' interface in Nagios XI. The 'Common Settings' tab is active, showing fields for 'Host Name' (Linux server), 'Alias' (Linux server), 'Address' (192.168.242.133), and 'Display name'. There are also buttons for 'Manage Parents', 'Manage Templates', and 'Manage Host Groups', all showing a count of 0. An 'Active' checkbox is checked. On the right, the 'Check command' is set to 'check-host-alive', and the 'Command view' shows the command: '\$USER1\$/check_icmp -H \$HOSTADDRESS\$ -w 3000.0,80% -c 5000.0,100% -p 5'. Below this are eight argument input fields labeled '\$ARG1\$' through '\$ARG8\$'. At the bottom right, there are buttons for 'Add Arguments +', 'Delete Arguments -', and 'Run Check Command'. At the bottom left, there are 'Save' and 'Cancel' buttons.

Using The Core Config Manager For Host Management In Nagios XI 2024 And 2026

5. All fields labeled with an asterisk are required fields.
6. Use the **Manage Parents** button to associate parent host(s) for the host.
 - a. Parents are used to specify network configuration connections.
7. Use the **Manage Templates** button to associate template(s) to the host.
 - a. Templates provide a method to push the same host setting to similar hosts.
8. Use the **Manage Host Groups** button to associate existing host group(s) to the host.
 - a. Host groups are a way to group similar hosts together.
9. On the previous screenshot of the **Common Settings** tab you'll notice that the **Active checkbox** is checked. If this box is un-checked the host configuration won't be put into production when Apply Configuration is performed. However, the settings will remain in Configuration Manager until you activate the host object.
10. To define the check command for this host, you select the appropriate command from the **Check command** drop down list.
 - a. On the previous screenshot of the **Common Settings** tab, you will see that check-host-alive is selected.
 - b. Every command in the **Check command** drop-down list is associated with a set of Nagios Core commands and arguments, which are shown in the Command view field. In this example there are no additional parameters required for the \$ARGx\$ fields.
 - c. For more detailed descriptions of Nagios commands see the following documentation: <https://assets.nagios.com/downloads/nagioscore/docs/nagioscore/4/en/objectdefinitions.html#command>
11. The **Check Settings** tab allows you to specify the settings for frequency of checks and the host state.

Using The Core Config Manager For Host Management In Nagios XI 2024 And 2026

Host Management

Common Settings ✓ Check Settings Alert Settings Misc Settings

Initial state
Down Up Unreachable

Check Interval [] min

Retry interval [] min

Max check attempts * 5 attempts

Active checks enabled
On Off Skip Null

Passive checks enabled
On Off Skip Null

Check period *
24x7

Freshness threshold [] sec

Check freshness
On Off Skip Null

Obsess over host
On Off Skip Null

Event handler []

Event handler enabled
On Off Skip Null

Low flap threshold [] %

High flap threshold [] %

Flap detection enabled
On Off Skip Null

Flap detection options
Down Up Unreachable

Retain status information
On Off Skip Null

Retain non-status information
On Off Skip Null

Process perf data
On Off Skip Null

Save Cancel

12. If a problem is detected with a connection, you can specify the details of how the problem is handled.
 - a. You will notice a lot of options have **Skip** chosen. This means that the setting is not being directly defined on the host object, this prevents any settings defined in templates from being overwritten.

Using The Core Config Manager For Host Management In Nagios XI 2024 And 2026

- b. If you look at the previous **Manage Templates** screenshot, you will see the template `xiwizard_genericnetdevice_host` is being used, which has these settings applied (as well as that template using another template).

13. The **Alert Settings** tab allows you to specify your notification settings.

The screenshot shows the 'Host Management' interface with the 'Alert Settings' tab selected. The interface includes several sections for configuring notifications:

- Common Settings**: Includes 'Manage Contacts' (0) and 'Manage Contact Groups' (0).
- Notification period**: A dropdown menu set to '24x7'.
- Notification options**: A row of buttons for 'Down', 'Unreachable', 'Recovery', 'Flapping', and 'Scheduled Downtime'.
- Notification interval**: An input field with a 'min' unit selector.
- First notification delay**: An input field with a 'min' unit selector.
- Notification enabled**: A row of buttons for 'On', 'Off', 'Skip', and 'Null', with 'Skip' selected.
- Stalking options**: A row of buttons for 'Down', 'Up', 'Unreachable', 'Notification', and 'None'.

At the bottom, there are 'Save' and 'Cancel' buttons.

Using The Core Config Manager For Host Management In Nagios XI 2024 And 2026

14. Use the **Manage Contacts** and **Manage Contact Groups** buttons to associate your existing contacts and contact groups with this host.

The screenshot shows the 'Host Management' interface in Nagios XI. The 'Misc Settings' tab is active, displaying various configuration options for a host. The interface is organized into two main columns. The left column contains fields for 'Notes', 'VRML Image', 'Notes URL', 'Status Image', 'Action URL', 'Icon Image', and 'Icon image 'alt' text'. The right column contains fields for '2D coords' (x,y) and '3D coords' (x,y,z). Below these is a 'Custom Variables' section with a 'Manage Custom Variables' button and a 'Use this configuration as a template' section with a 'Generic name' field. At the bottom left, there are 'Save' and 'Cancel' buttons.

15. The **Misc Settings** tab is for defining additional host information and can be used for adding notes, icon images, and for setting Free variable definitions.

- a. There are a few important things that you should note about Free variables (custom object variables):
 - i. Custom variable names must begin with an underscore (`_`) to prevent name collision with standard variables.
 - ii. Custom variable names are case-insensitive
 - iii. Custom variables are inherited from object templates like normal variables
 - iv. Scripts can reference custom variable values with macros and environment variables
 - v. For additional information about using custom object variables see the following document: [Understanding Nagios XI Notification Variables](#)

Using The Core Config Manager For Host Management In Nagios XI 2024 And 2026

16. Once you've finished entering information for your new host, click the **Save** button to return to the **Host Management** page.
17. Click **Apply Configuration** to restart Nagios XI and put the new settings into effect. Nagios XI will verify the settings and display a success message that the host was set up correctly.

Modifying Hosts

Hosts can be modified by clicking the Modify icon  OR the host name itself from the Host Management page.

This will bring up the same set of tabbed menus covered in the [Adding Hosts](#) section of this tutorial. Refer to that section for a detailed walk through of the tabs that control host settings.

Deleting / Deactivating Hosts

1. Hosts can be deleted by selecting the **Delete** icon from the **Host Management** page.
2. Multiple hosts can also be deleted by selecting the desired hosts in the left checkbox column and then selecting **Delete** from the **With checked** drop-down list.
3. Hosts can be activated or deactivated by clicking on the **Yes** or **No** link under the **Active** column.
 - a. Deactivating a host is the same as deleting it as far as the monitoring engine is concerned, but this does preserve the host's configuration within Nagios XI if you want to recover it later. You can also deactivate multiple hosts using the With checked drop-down list.
- **Note:** Hosts can only be deleted/deactivated once their dependent services are also deleted/deactivated.
4. To see if a host has dependencies click the **Relationships** icon to check for dependencies.


Using The Core Config Manager For Host Management In Nagios XI 2024 And 2026

Config Name	Service Description
localhost	↔ PING
localhost	↔ Root Partition
localhost	↔ Current Users
localhost	↔ Total Processes
localhost	↔ Current Load
localhost	↔ Swap Usage
localhost	↔ Memory Usage
localhost	↔ SSH


5. This information will be displayed in a pop-up window. In the screenshot you can see this host has multiple services that prevent it from being deleted or de-activated.
6. To delete a host with dependencies, make sure all the services assigned to this host are deleted first.
7. To remove dependent services, click the **Services** link to bring up the **Service Management** page.

Using The Core Config Manager For Host Management In Nagios XI 2024 And 2026


- Use the **Config Name** drop down list to bring up all services being used by the selected host.



- Click the **top-left Checkbox**, this will select all the services in the list. From the **With Checked** drop-down list select **Delete** and then click the **Go** button.



- Once all dependent services have been deleted, return to the **Host Management** page and use the **Delete** icon to delete the host. If the host was deleted successfully, Nagios XI will display a



success message at the top of the page.

- If there are unresolved dependencies, Nagios XI will display an error message in red at the top of the page.


Using The Core Config Manager For Host Management In Nagios XI 2024 And 2026

11. Once the host is deleted, be sure to click **Apply Configuration** for the monitoring of the host (and services) to stop.

Copying Hosts

Copying a host is a quick way to start monitoring a new host, especially if the new host will have similar (if not the same) monitoring settings.

1. To copy a host, click the **Copy** icon from the **Host Management** page for the host you want to copy.
2. If you wanted to copy multiple hosts, select the desired hosts you want to copy in the left checkbox column and then select **Copy** from the **With checked** drop-down list.
3. After creating a copy, the duplicate host(s) will be assigned a default name that will need to be changed. Host copies are also inactive by default and will need to be activated for monitoring use.





4. To rename and activate the copied host click the **Modify** icon.
5. Change the entry for **Host Name** to a valid name.
6. You will also need to change the address to the address of the new host that will be monitored.
7. To activate the host copy, click the **Active** checkbox.
8. Once changes are complete click the **Save** button.
9. Click **Apply Configuration** to start monitoring the new host.

Using The Core Config Manager For Host Management In Nagios XI 2024 And 2026

Managing Host Groups


Host Groups allow you to group hosts in a logical manner, making it easier for users to get a quick view of their network infrastructure. They will not have an impact on the notifications or access control but will make it easier for both your users to grasp what they are looking at and for you as the administrator to quickly pinpoint where problems are occurring.

1. You can define new host groups by selecting the **Host Groups** menu item (under Monitoring) from the Configuration menu and clicking the **+ Add New** button.



Using The Core Config Manager For Host Management In Nagios XI 2024 And 2026

2. You will need to give the new **Host** group a name and description.




The screenshot shows the 'Host Group Management' interface in Nagios XI. The form is titled 'Host Group Management' and contains several input fields and buttons. On the left side, there are fields for 'Host Group Name' (containing 'Linux hosts'), 'Alias' (containing 'important linux hosts'), 'Notes', 'Notes URL', and 'Action URL'. Below these fields is a checkbox labeled 'Active' which is checked. At the bottom left are 'Save' and 'Cancel' buttons. On the right side, under the heading 'Assign Memberships', there are two buttons: 'Manage Hosts' with a '0' indicator and 'Manage Host Groups' with a '0' indicator.

3. You can add hosts or host groups to the newly created host group using the **Manage Hosts** button and **Manage Host Groups** buttons.
4. When you are finished click the **Save** button.
5. Remember to **Apply Configuration** when you are done making configuration changes.

Using The Core Config Manager For Host Management In Nagios XI 2024 And 2026

Using Host Templates

Host templates can be created by selecting the Host Templates link from the **Configuration** menu templates. This will bring up the **Host Template Management** page.




Many administrators prefer to create their own host templates to specify default values for check commands, notification settings, and contact settings. Templates can also inherit values from other templates, which can be useful for creating universal settings for hosts and services.

From the Host Template Management page, you can add, modify, copy, or delete existing templates. Nagios XI comes with an existing selection of host templates that can be used or modified for your monitoring needs. The Host Template Management page uses the same layout and menu system as the Host Management page. See the above section on [Adding Hosts](#) for details on navigating the user interface.

- **Note:** Templates can inherit values from other parent templates. If a template has a parent template assigned via the Manage Templates button, it will inherit that template's settings. Be careful when modifying the "generic" templates, as these are the main parent templates, and this may affect many of the other templates that inherit values from it.

Using The Core Config Manager For Host Management In Nagios XI 2024 And 2026




When you need to update a configuration setting for multiple hosts you can use the **Bulk Modifications Tool**, which is located under the Tools menu. This allows you to make a change like adding a contact to a selection of hosts, instead of manually editing each host.

The **Bulk Modifications Tool** is available when you have the Nagios XI Enterprise License. If you are not licensed for the Enterprise Edition you can enable a 30-day trial which allows you to use all the features of the Bulk Modifications Tool.

Using The Core Config Manager For Host Management In Nagios XI 2024 And 2026

The screenshot below shows the location and options of the **Bulk Modifications Tool**.



Finishing Up

This completes the documentation on using the Core Config Manager for Host Management in Nagios XI 2024 and 2026. If you have additional questions or other support-related questions, please visit us at our Nagios Support Forum, Nagios Knowledge Base, or Nagios Library:

[Visit Nagios Support Forum](#)

[Visit Nagios Knowledge Base](#)

[Visit Nagios Library](#)